

MIMICA command

There is a new special command for Portuguese Mountbatten. This command is used to turn on or off displaying accents on Mimic display.

MIMICA – toggles between displaying and not displaying accented characters.

Comment:

There are two revisions of Mimic displays:

- version capable of displaying accented characters
- version not capable of displaying accented characters (strange characters are displayed instead)

If Mountbatten is switched to mode with accented characters all accents will be displayed properly on capable version of Mimic. In this mode non capable version of Mimic will display strange characters. In mode without accents both version of Mimic will display characters from Latin alphabet instead of accented characters.

After hard reset Mountbatten is configured to display accented characters. If this setting is changed by the user, it is saved in memory until next use of command MIMICA or hard reset.

This command is available since build 74 (v93cs23 b74, v93cv23 b74) of Mountbatten firmware.